

# The application of variable-dependent macro on SDTM conversion

Mindy Wang, Independent Consultant, North Potomac, MD

## ABSTRACT

In clinical trials and many other research fields, repetitive statements happen very often. This paper illustrates how to deal with the same task with three different approaches. The first approach uses simple copy and paste any SAS® beginner can do. The second approach uses a simple macro program to make the task more efficient, and reduce the length of the program. To further improve the program and to make the program more adaptable to other projects, the third approach uses variable-dependent macros which minimize tedious typing, eliminate possible human errors, and ensure the accuracy of data.

## INTRODUCTION

This program is based on a study to convert EG data to SDTM formats in a clinical trial. However, the SAS codes can be rewritten easily to handle other fields of study as well. The parameter variables came in as a csv file. What we need to accomplish is to do the repetitive tasks which apply to all the variables specified in the parameter variables data set that are in csv formats. Following is the screen print of the parameter data (Display 1).

A	B	C	D	E	F	G	H	I	J	K
1 varout	varin	test	type	egcat	unit					
2 intp	ecgtp	OVERALL INTERPRETATION	c	FINDING						
3 hr1	hr1	Heart Rate Measurement 1	n	MEASUREMENT	hru_					
4 hr2	hr2	Heart Rate Measurement 2	n	MEASUREMENT	hru_					
5 hr3	hr3	Heart Rate Measurement 3	n	MEASUREMENT	hru_					
6 hrmean	hrm	Summary (Mean) Heart Rate	n	MEASUREMENT	hru_					
7 pr1	pri1	PR Duration Measurement 1	n	MEASUREMENT	priu_					
8 pr2	pri2	PR Duration Measurement 2	n	MEASUREMENT	priu_					
9 pr3	pri3	PR Duration Measurement 3	n	MEASUREMENT	priu_					
10 prmean	prim	Summary (Mean) PR Duration	n	MEASUREMENT	priu_					
11 qrs1	qrsi1	QRS Duration Measurement 1	n	MEASUREMENT	qrsiu_					
12 qrs2	qrsi2	QRS Duration Measurement 2	n	MEASUREMENT	qrsiu_					
13 qrs3	qrsi3	QRS Duration Measurement 3	n	MEASUREMENT	qrsiu_					
14 QRSDUR	qrsim	Summary (Mean) QRS Duration	n	MEASUREMENT	qrsiu_					
15 qtc1	qtc1	QTc Bazetts Formula Measurement 1	n	MEASUREMENT	qtcu_					
16 qtc2	qtc2	QTc Bazetts Formula Measurement 2	n	MEASUREMENT	qtcu_					
17 qtc3	qtc3	QTc Bazetts Formula Measurement 3	n	MEASUREMENT	qtcu_					
18 QTCBMEAN	QTCBM	Summary (Mean) QTc Bazetts Formula	n	MEASUREMENT	qtcu_					
19 qtcf1	qtcf1	QTc Fridericias Formula Measurement 1	n	MEASUREMENT	qtcfu_					
20 qtc2	qtcf2	QTc Fridericias Formula Measurement 2	n	MEASUREMENT	qtcfu_					
21 qtc3	qtcf3	QTc Fridericias Formula Measurement 3	n	MEASUREMENT	qtcfu_					
22 QTCFMEAN	QTCFM	Summary (Mean) QTc Fridericias Formula	n	MEASUREMENT	qtcfu_					
23 qt1	qti1	QT Duration Measurement 1	n	MEASUREMENT	qtui_					
24 qt2	qti2	QT Duration Measurement 2	n	MEASUREMENT	qtui_					
25 qt3	qti3	QT Duration Measurement 3	n	MEASUREMENT	qtui_					
26 QTMEAN	qtim	Summary (Mean) QT Duration	n	MEASUREMENT	qtui_					

Display 1. The Original Parameter Data

## COPY AND PASTE METHOD

Copy and paste method is the easiest way we can do to accomplish repetitive tasks. No extensive knowledge of SAS is needed. Following copy and paste method codes illustrate this easy method. However, the downside of this method is that it takes busy work. If we need to repeat it three times, it won't be too big a deal. However, if we need to repeat it 50 times or 100 times, the task will be very tedious. In addition, as we use more manual manipulation, it is more likely we might make mistakes along the way.

It is always a good idea to make the program work in plain text and then try to improve it by incorporating macros. For example we start out with plain text, copy it a few times, and figure out which variables need to be changed, and then incorporate Macro Definition to make it more efficient.

Following is the illustration of copy and paste method.

```
Data eg2;
  set sdtm.ert;
  length egtest egtestcd egcat egorres egstresc $ 200 egstresu egorresu $ 8;
  egtestcd = " " ;
  egorres = " " ;
  egstresc = " " ;
  egtest = " " ;
  egtestcd = "INTP" ;
  egtest = upcase("OVERALL INTERPRETATION");
  egorres = left(trim(upcase ( ecgitp_ ))) ;
  egstresc = upcase ( egorres ) ;
  egcat="FINDING";
  if ( egorres ne " " ) then output ;
  drop ecgitp: ;

  egtestcd = " " ;
  egorres = " " ;
  egstresc = " " ;
  egtest = " " ;
  egtestcd = "HR1" ;
  egtest = upcase("Heart Rate Measurement 1");
  if ( hr1 ne . ) then do ;
    egorres = trim ( left ( put ( hr1 , best. ))) ;
    egstresn = hr1 ;
    egorresu=hru_ ;
    egstresu=hru_ ;
  end ;
  egstresc = upcase ( egorres ) ;
  egcat="MEASUREMENT";
  if ( egorres ne " " ) then output ;
  drop hr1: hru_ ;

  egtestcd = " " ;
  egorres = " " ;
  egstresc = " " ;
  egtest = " " ;
  egtestcd = "HR2" ;
  egtest = upcase("Heart Rate Measurement 2");
  if ( hr2 ne . ) then do ;
    egorres = trim ( left ( put ( hr2 , best. ))) ;
    egstresn = hr2 ;
    egorresu=hru_ ;
    egstresu=hru_ ;
  end ;
  egstresc = upcase ( egorres ) ;
  egcat="MEASUREMENT";
  if ( egorres ne " " ) then output ;
```

```

drop hr2: hru_;

egtestcd = " " ;
egorres = " " ;
egstresc = " " ;
egtest = " " ;
egtestcd = "HR3" ;
egtest = upcase("Heart Rate Measurement 3");
if ( hr3 ne . ) then do ;
    egorres = trim ( left ( put ( hr3 , best. ))) ;
    egstresn = hr3 ;
    egorresu=hru_ ;
    egstresu=hru_ ;
end ;
egstresc = upcase ( egorres ) ;
egcat="MEASUREMENT";
if ( egorres ne " " ) then output ;
drop hr3: hru_;

egtestcd = " " ;
egorres = " " ;
egstresc = " " ;
egtest = " " ;
egtestcd = "HRMEAN" ;
egtest = upcase("Summary (Mean) Heart Rate");
if ( hrm ne . ) then do ;
    egorres = trim ( left ( put ( hrm , best. ))) ;
    egstresn = hrm ;
    egorresu=hru_ ;
    egstresu=hru_ ;
end ;

egstresc = upcase ( egorres ) ;
egcat="MEASUREMENT";
if ( egorres ne " " ) then output ;
drop hrm: hru_;

.....
run;

```

## SIMPLE MACRO METHOD

The following method takes a step further and substitutes the variables need to be changed in keyword parameters. We only need to define the macro program once. By invoking the macro with different parameters, we can achieve the same goal with a much shorter and efficient program. However, when the there are many sets of keyword parameters, even writing up the commands to invoke the macro takes substantial time. There is still room for improvement. In the section following this one, the program is further improved by incorporating variable dependent macro.

```

%macro setx (varout=, varin=, test=, type=, egcat=, unit=);
    %if ( &varin eq ) %then
        %do ;
            %let varin = &varout;
        %end ;
    egtestcd = " " ;
    egorres = " " ;
    egstresc = " " ;
    egtest = " " ;
    egtestcd = %upcase ( "&varout" ) ;
    egtest = upcase("&test");
    %if ( &type eq c ) %then
        %do ;

```

```

    egorres = left(trim(uppercase ( &varin._ ))) ;
%end ;
%else %if ( &type eq n ) %then
%do ;
    if ( &varin ne . ) then
    do ;
        egorres = trim ( left ( put ( &varin , best. ))) ;
        egstresn = &varin ;
        egorresu=&unit ;
        egstresu=&unit ;
    end ;
%end ;
egstresc = uppercase ( egorres ) ;
egcat="&egcat";
if ( egorres ne " " ) then
    output ;
drop &varin: &unit;
%mend setx ;

data eg2;
    set sdtm.ert;
    length egtest egtestcd egcat egorres egstresc $ 200 egstresu egorresu $ 8;
    %setx (varout=intp, varin=ecgtp, test=OVERALL INTERPRETATION, type=c,
egcat=FINDING);
    %setx (varout=hrl, varin=hrl, test=Heart Rate Measurement 1, type=n,
egcat=MEASUREMENT, unit=hru_);
.....
Run;

```

## VARIABLE DEPENDENT MACRO METHOD

With variable dependent macro, the utmost advantage is that there is no need to type in the parameters for macro manually, since it is already in a csv file. Without the manual manipulation, chances for typing errors are largely reduced. The parameters only need to be imported. In the data step call symputx is used to save the parameters into macro variables with corresponding record number. In this case, since we don't have any do loop in the data step. The number of record would be consistent with the number of iteration. We can keep `_n_` as our record ID. Then for each record ID, we use call symputx to save each parameter to macro variable with corresponding record ID.

For example, we save the value of the first parameter named "varout" in the first record, and call the macro variable "varout1". We do the same for the other variables. Therefore for record ID 1, we have saved macro variables "varin1", "test1", "type1", "egcat1", "unit1" as well. After we saved the macro variables for the first record id, the data step saved the macro variables for record ID 2, as "varout2", "varin2", "test2", "type2", "egcat2", and "unit2". Then we saved the macro variables for other record ID until we reach the end of the parameter data set. We can then use %put n, %put varout1, etc. to see if the program is doing what we expected and print out the data set one to verify.

The variable dependent program can be adapted to difference projects very easily. As long as the parameter is in a csv or excel file, we can just import the parameter data in and very little modification is needed to make it work. Also, if we need to make any change, we only need to make change in the csv file once. We don't need to go through all 33 different places in the program to make the change. Unlike in the first two methods which a lot of manual manipulation is needed, this method is very easy for new parameters.

```

proc import datafile = "C:\Documents and
Settings\mindy.wang\Desktop\SAS\NESUG_2010\eg_categories.csv"
    out = work.zero dbms = dlm replace;
    guessingrows=200;
delimitter = ',';
run;

```

```

data one;
  set zero end=eof;
  n=put(_n_,2.);
  call symputx('varout' ||left(n), varout);
  call symputx('varin' ||left(n), varin);
  call symputx('test' ||left(n), test);
  call symputx('type' ||left(n), type);
  call symputx('egcat' ||left(n), egcat);
  call symputx('unit' ||left(n), unit);
  if eof then call symputx('n',n);
run;

/*CHECK THE NUMBER OF CASES*/
%put n=&n;
proc print data=one;
run;

%macro vdm (varout=, varin=, test=, type=, egcat=, unit=);
%do i=1 %to &n;
  %if ( &&varin&i eq ) %then
    %do ;
      %let varin = &&varout&i;
    %end ;
    egtestcd = " " ;
    egorres = " " ;
    egstresc = " " ;
    egtest = " " ;
    egtestcd = %upcase ( "&&varout&i" ) ;
    egtest = upcase("&&test&i");
    %if ( &&type&i eq c ) %then
      %do ;
        egorres = left(trim(upcase ( &&varin&i.._ ))) ;
      %end ;
    %else %if ( &&type&i eq n ) %then
      %do ;
        if ( &&varin&i ne . ) then
          do ;
            egorres = trim ( left ( put ( &&varin&i , best. )) ) ;
            egstresn = &&varin&i ;
            egorresu=&&unit&i;
            egstresu=&&unit&i ;
          end ;
        %end ;
        egstresc = upcase ( egorres ) ;
        egcat="&&egcat&i";
        if ( egorres ne " " ) then
          output ;
          drop &&varin&i: &&unit&i;
        %end;
      %mend vdm;
%end;

data eg1;
  set sdtm.ert;
  length egtest egtestcd egcat egorres egstresc $ 200 egstresu egorresu $ 8;
  %vdm
run;


```

## OTHER WAYS TO REDUCE TYPING

Sometimes, it is equally important for our co-workers to understand our SAS programs, as to make our SAS programs robust and easier to adapt to other projects. Suppose your co-workers don't use macros at all, there are

still ways that you can use the variable dependent macros to eliminate manually coping and pasting. You can always set "options mprint". That way, there will be a translation of what the macro does in the log, then copy the log to the program editor and replace "MPRINT(VDM):" with blank space.

Following is the screen print of the codes that mprint generated in the log (Display2).



## Display2: The Log After Using Mprint


An even better alternative is using mprint and mfile options together. Following codes (before invoking the macro) would save the plain text generated by mprint to a SAS file without doing the copy and paste. SAS automatically generates the plain text in the file called macode.sas for you.

```

filename mprint 'desktop\macode.sas';
options mprint mfile;

```

Following is a screen print of the codes that are generated and saved by mprint and mfile (Display 3).



### Display 3. Codes That Are Generated and Saved by Mprint and Mfile

Suppose your co-workers just started to use macro, they understand the simple macro, but the variable dependent macro is way too abstract for them. You can still use part of the variable dependent macro to make your life easier. The following codes will generate the command codes in a text file. Then you can copy and paste the command lines to the simple macro method program to invoke the macro (Display 4).

```

data one;
  set zero end=eof;
  n=put(_n_,2.);
  call symputx('varout' ||left(n), varout);
  call symputx('varin' ||left(n), varin);
  call symputx('test' ||left(n), test);
  call symputx('type' ||left(n), type);
  call symputx('egcat' ||left(n), egcat);
  call symputx('unit' ||left(n), unit);
  if eof then call symputx('n',n);
run;

%macro string;
  %do i=1 %to &n;
    stri='%setx (varout=' ||"&varout&i"||', varin=' ||"&varin&i"||', test=' ||
      "&test&i"||', type=' ||"&type&i"||', egcat=' ||"&egcat&i"||
      ', unit=' ||"&unit&i"||)';
    put stri;
  %end;
%mend string;

data _null_;
  length stri $250;


```

```

file 'desktop\eg_string.txt';
%string
run;

```

The following are the command codes generated by the above SAS codes.



```

%setx (varout=intp, varin=ecgtp, test=OVERALL INTERPRETATION, type=c, egcat=FINDING, unit= )
%setx (varout=hr1, varin=hr1, test=Heart Rate Measurement 1, type=n, egcat=MEASUREMENT, unit=hru_)
%setx (varout=hr2, varin=hr2, test=Heart Rate Measurement 2, type=n, egcat=MEASUREMENT, unit=hru_)
%setx (varout=hr3, varin=hr3, test=Heart Rate Measurement 3, type=n, egcat=MEASUREMENT, unit=hru_)
%setx (varout=hrmean, varin=hrm, test=Summary (Mean) Heart Rate, type=n, egcat=MEASUREMENT, unit=hru_)
%setx (varout=pr1, varin=pr1, test=PR Duration Measurement 1, type=n, egcat=MEASUREMENT, unit=priu_)
%setx (varout=pr2, varin=pr2, test=PR Duration Measurement 2, type=n, egcat=MEASUREMENT, unit=priu_)
%setx (varout=pr3, varin=pr3, test=PR Duration Measurement 3, type=n, egcat=MEASUREMENT, unit=priu_)
%setx (varout=prmean, varin=prim, test=Summary (Mean) PR Duration, type=n, egcat=MEASUREMENT, unit=priu_)
%setx (varout=qrs1, varin=qrs1, test=QRS Duration Measurement 1, type=n, egcat=MEASUREMENT, unit=qrsiu_)
%setx (varout=qrs2, varin=qrs2, test=QRS Duration Measurement 2, type=n, egcat=MEASUREMENT, unit=qrsiu_)
%setx (varout=qrs3, varin=qrs3, test=QRS Duration Measurement 3, type=n, egcat=MEASUREMENT, unit=qrsiu_)
%setx (varout=qrsdur, varin=qrsim, test=Summary (Mean) QRS Duration, type=n, egcat=MEASUREMENT, unit=qrsiu_)
%setx (varout=qtcb1, varin=qtcb1, test=QTc Bazetts Formula Measurement 1, type=n, egcat=MEASUREMENT, unit=qtcbu_)
%setx (varout=qtcb2, varin=qtcb2, test=QTc Bazetts Formula Measurement 2, type=n, egcat=MEASUREMENT, unit=qtcbu_)
%setx (varout=qtcb3, varin=qtcb3, test=QTc Bazetts Formula Measurement 3, type=n, egcat=MEASUREMENT, unit=qtcbu_)
%setx (varout=qtcbmean, varin=qtcbm, test=Summary (Mean) QTc Bazetts Formula, type=n, egcat=MEASUREMENT, unit=qtcbu_)
%setx (varout=qtcf1, varin=qtcf1, test=QTc Fridericias Formula Measurement 1, type=n, egcat=MEASUREMENT, unit=qtcfu_)
%setx (varout=qtcf2, varin=qtcf2, test=QTc Fridericias Formula Measurement 2, type=n, egcat=MEASUREMENT, unit=qtcfu_)
%setx (varout=qtcf3, varin=qtcf3, test=QTc Fridericias Formula Measurement 3, type=n, egcat=MEASUREMENT, unit=qtcfu_)
%setx (varout=qtcfmean, varin=qtcfm, test=Summary (Mean) QTc Fridericias Formula, type=n, egcat=MEASUREMENT, unit=qtcfu_)
%setx (varout=qt1, varin=qt1, test=QT Duration Measurement 1, type=n, egcat=MEASUREMENT, unit=qtiu_)
%setx (varout=qt2, varin=qt2, test=QT Duration Measurement 2, type=n, egcat=MEASUREMENT, unit=qtiu_)
%setx (varout=qt3, varin=qt3, test=QT Duration Measurement 3, type=n, egcat=MEASUREMENT, unit=qtiu_)
%setx (varout=qtmean, varin=qtim, test=Summary (Mean) QT Duration, type=n, egcat=MEASUREMENT, unit=qtiu_)
%setx (varout=rr1, varin=rr1, test=RR Duration Measurement 1, type=n, egcat=MEASUREMENT, unit=rriu_)
%setx (varout=rr2, varin=rr2, test=RR Duration Measurement 2, type=n, egcat=MEASUREMENT, unit=rriu_)
%setx (varout=rr3, varin=rr3, test=RR Duration Measurement 3, type=n, egcat=MEASUREMENT, unit=rriu_)
%setx (varout=rrmean, varin=rrim, test=Summary (Mean) RR Duration, type=n, egcat=MEASUREMENT, unit=rriu_)
%setx (varout=stseg, varin=stseg, test=ST Segment Evaluation, type=c, egcat=FINDING, unit= )
%setx (varout=uwave, varin=uwave, test=U wave Evaluation, type=c, egcat=FINDING, unit= )
%setx (varout=uwave, varin=uwave, test=U wave Evaluation, type=c, egcat=FINDING, unit= )
%setx (varout=EXSYSTOL, varin=ectopy, test=Cardiac Rhythm Disturbances, type=c, egcat=FINDING, unit= )

```

#### Display 4. The Command Codes Generated by The Above SAS Codes

### CONCLUSIONS

The variable dependent macro method is certainly the best method to use among all three methods discussed above. Not only it has minimized typing, but it is also most adaptable to other projects. Oftentimes, we have time constraint to get thing done at certainly time, copy and paste method is a sure thing we can get it done. However, we should strive to rewrite the programs so it is easier to adapt to new situation. Even though at first it takes time to develop; In the long run, the variable dependent macro really saves time. Even if we need to increase the readability of Macro, the knowledge of variable dependent macro still makes our life easier by generating the codes that can be easily understood without a lot of manual manipulation as illustrated in the above two examples.

### REFERENCES:

- SAS Macro Language 1: Essentials Course Notes
- Carpenter, Art (2004) Carpenter's Guide to SAS Macro Language Second Edition
- Burlew, Michele M. (2006) SAS Macro Programming Made Easy

### ACKNOWLEDGMENTS

Many thanks to Kevin Chung in providing the valuable suggestions for the variable-dependent macro.



## **CONTACT INFORMATION**

Your comments and questions are valued and encouraged. Please contact the author at:

Name: Mindy Wang

Enterprise: Independent Consultant

Address: 14412 Stonebridge View Dr.

City, State ZIP: North Potomac, MD 20878

Phone: (240) 855-3479

Email: [ymindywang@yahoo.com](mailto:ymindywang@yahoo.com)

SAS and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries. ® indicates USA registration. Other brand and product names are trademarks of their respective companies.